

This set of barcodes should be used only when suggested by WordStock Support.

1. Dual port RS-232C



6. Xon/Xoff



2. 9600



7. 1 stop bit



3. None



8. 8-bit



4. Do not check parity



9. Talk & Receive host only




5. None



10. Delete all code types



11. Add UPC-A




17. Either scanner port



12. Add UPC-E



18. UPC-A



13. Add EAN-8



19. Send ^



14. Add EAN-13



20. Send all data that remains



15. Autodiscriminate UPC/EAN Supplementals



21. Send Control M



16. Erase all rules



22. Save Rule



23. Either scanner port



29. Either scanner port



24. UPC-E



30. EAN-8



25. Send ~



31. Send }



26. Send all data that remains



32. Send all data that remains



27. Send Control M



33. Send Control M



28. Save rule



34. Save rule



35. Either scanner port



41. Any magstripe reader



36. EAN-13



42. Send ;



37. Send {



43. Skip ahead 1 character



38. Send all data that remains



44. Send up to character*



39. Send Control M



45. [no text]



40. Save rule



46. Send =



47. Skip ahead 1 character



48. Send all data that remains



49. Send Control M



50. Save rule



51. Press the reset button on the Omnilink box
(opposite the red and green lights)